


**Example 10** Heat conduction with a heat source



BC1: at  $r = 0$ ,  $q_r$  is not infinite

BC2: at  $r = R$ ,  $T = T_0$

**Energy balance around shell**

Rate of energy in - Rate of energy out + Rate of energy production = 0

$$(4\pi r^2)q_r|_r - (4\pi(r + \Delta r)^2)q_r|_{r+\Delta r} + (4\pi r^2 \Delta r)S_e = 0$$

Approximate  $\Delta r \ll r$  so  $r + \Delta r \approx r$  we get

$$(4\pi r^2)q_r|_r - (4\pi r^2)q_r|_{r+\Delta r} + (4\pi r^2 \Delta r)S_e = 0$$

Divided through equation by  $4\pi \Delta r$  and taking limit  $\Delta r \rightarrow 0$  we obtain

$$-\lim_{\Delta r \rightarrow 0} \frac{(r^2 q_r)|_{r+\Delta r} - (r^2 q_r)|_r}{\Delta r} = -S_e r^2$$

The expression on the left side is the first derivative of  $r^2 q_r$  with respect to  $r$ , so that equation becomes

$$\frac{d}{dr}(r^2 q_r) = S_e r^2$$
$$\int d(r^2 q_r) = \int S_e r^2 dr + C_1$$
$$r^2 q_r = \frac{S_e r^3}{3} + C_1$$

The equation may be integrated to give

$$q_r = \frac{S_e r}{3} + \frac{C_1}{r^2}$$

Apply BC1: at  $r = 0$ ,  $q_r$  is not infinite

$$q_r = \frac{S_e(0)}{3} + \frac{C_1}{(0)^2}$$

$$\text{finite} = \text{finite} + \text{infinite}$$

The term  $C_1$  must be forced to be zero in order to make the right hand side is finite we get

$$q_r = \frac{S_e r}{3}$$

Apply Fourier's law:  $q_r = -k \frac{dT}{dr}$

$$-k \frac{dT}{dr} = \frac{S_e r}{3}$$

Assume  $k$  is constant and indefinite integrate the equation we obtain

$$\int dT = - \int \frac{S_e r}{3k} dr$$
$$T = - \frac{S_e r^2}{6k} + C_2$$

Apply BC2: at  $r = R$ ,  $T = T_0$

$$T_0 = - \frac{S_e R^2}{6k} + C_2$$

$$C_2 = T_0 + \frac{S_e R^2}{6k}$$

Substitute  $C_2$  into the equation so the equation becomes

$$T - T_0 = \frac{S_e R^2}{6k} \left[ 1 - \left( \frac{r}{R} \right)^2 \right]$$

Once the temperature and heat flux distributions are known, various information about the system may be obtained.

(i) *Maximum temperature rise (at  $r = 0$ )*

$$T_{max} - T_0 = \frac{S_e R^2}{6k}$$

(ii) *Average temperature rise*

$$\bar{T} - T_0 = \frac{\int_0^{2\pi} \left( \int_0^R (T(r) - T_0) r dr \right) d\theta}{\int_0^{2\pi} \left( \int_0^R r dr \right) d\theta} = \frac{S_e R^2}{12k}$$

(iii) *Heat outflow at the surface (for radius R of sphere)*

$$Q|_{r=R} = 4\pi R^2 \cdot q_r|_{r=R} = 4\pi R^2 \cdot \frac{S_e R}{3} = \frac{4}{3} \pi R^3 \cdot S_e$$